User Software :: CR-Tools :: The CalTable System

- Usage of the CalTables
- Fields of the official LOPES CalTable
- Keywords of the official LOPES CalTable
- (Internal) Structure of the CalTables

Usage of the CalTables

The CalTables are a system to store and retrieve calibration and other meta-data.

One piece of data (an atom) can be a string, a double, a dcomplex, an array of double or an array of dcomplex. Each atom is identified by its field name (which defines its type), the antenna ID, and the date for which it is valid.

A reading operation can look like this:

Notes:

- In the table.get() call you have to supply the correct type for the field you are requesting. E.g. if the field whose fieldName you asked for is of the type string, then the variable in which the data is to be stored also has to be of the type string. Otherwise the call returns false.
- In the table.get() call, if the fieldName of AntennaID does not exist the call returns false.
- In the table.get() call, if no valid data for the requested time is found the call returns false.

Writing to the CalTable is only slightly more complicated, but still should only be done by trained



Adding fields to a CalTable should only be done by experts, as the later performance can be improved

by taking advantage of the internal structure of the CalTables.

Fields of the official LOPES CalTable

This is the list of fields in the official LOPES CalTable.

The definition of the fields is also in the description of the column in the master table.

Field Name	Data Type	Desctription				
HWSetup	String	Status of the hardware setup. (Why has something in this subtable changed.)				
Position	Vector <double></double>	Relative antenna Position [Northing, Easting, Height] (in m) (Remark: This ordering is [Y-axis, X-axis, Z-axis]) Position [0,0,0] is the center of the KASCADE array.				
FrequencyBand	Vector <double></double>	Effective frequency band of this antenna [StartFreq, StopFreq] (in Hz)				
Polarization	String	Polarization direction of this antenna/channel. ("EW" for East-West (standard) or "NS" nor North-South)				
ElGainCal	Vector <double></double>	Gain calibration values. Multiply to the frequency domain lata to correct for the electronic gain. (I.e. the factor etween FFT and CalFFT, so square this value before pplying to power data.) Usually the values are positive, negative values correct for wrong orientation of the lipole.				
ElGainCalFreq	Vector <double></double>	Frequency axis for ElGainCal (in Hz). The vectors of ElGainCal and ElGainCalFreq have the same length, so the n-th value of ElGainCal belongs to the frequency stored in the n-th value of ElGainCalFreq				
PhaseCal	Vector <dcomplex></dcomplex>	Relative Phase calibration values. Multiply to the frequency domain data to correct for phase differences of the filters etc. Be careful during interpolation: ensure that abs(PhaseCal)==1				
PhaseCalFreq	Vector <double></double>	Frequency axis for PhaseCal (in Hz). Same structure a ElGainCalFreq for ElGainCal.				
Delay	Double	Relative delay of the antenna (in seconds).				
PhaseRefPhases	Vector <double></double>	Phase calibration reference phases (in degrees). E.g. for the calibration on the TV transmitter.				
PhaseRefFreqs	Matrix <double></double>	Freqency ranges for the phase calibration [[StartFreq, StopFreq] , [<band number="">]] (in Hz)</band>				
SampleJumps	Vector <double></double>	Jumps by how many samples are to be tried in the phase calibration routine. (Only needed for the reference - currently the first (ID: 10101) - antenna.)				
AntennaGainFaktor Array <double></double>		Array with the antenna gain faktors as they are eventually multiplied to the data: i.e. the value: 1/sqrt(Gain) (wit Gain==Directivity) with axes: [Frequency, Azimuth, Elevation]				
AntennaGainFaktFred	Vector <double></double>	Frequency axis for AntennaGainFaktor (in Hz)				

Field Name	Data Type	Desctription				
AntennaGainFaktAz	Vector <double></double>	Azimuth axis for AntennaGainFaktor 0=North, 90=East (in degrees)				
AntennaGainFaktEl	Vector <double></double>	Elevation axis for AntennaGainFaktor (in degrees)				
AntennaAziGain	Array <double></double>	The Antenna Gain Faktors for the azimuth polarization component. The value: 1/sqrt(Gain) (with Gain==Directivity) with axes: [Frequency, Azimuth, Elevation] (Identical axes as AntennaGainFaktor.)				
AntennaZeniGain	Array <double></double>	The Antenna Gain Faktors for the zenith polarization component. The value: 1/sqrt(Gain) (with Gain==Directivity) with axes: [Frequency, Azimuth, Elevation] (Identical axes as AntennaGainFaktor.)				
AntennaAziPhase	Array <double></double>	The Phase of the Antenna Gain for the azimuth polarization component. The phase angle in radians with axes: [Frequency, Azimuth, Elevation]				
AntennaZeniPhase Array <double></double>		The Phase of the Antenna Gain for the zenith polarization component. The phase angle in radians with axes: [Frequency, Azimuth, Elevation]				
PhaseRefAnt	Double	The ID of the reference antenna, to which phase differences for the phase calibration are measured. (Set to -1 to switch off phase calibration.)				

Keywords of the official LOPES CalTable

This is the list of keywords in the LOPES CalTable, that can be read with GetKeyword():

Keyword Name	Data Type	Desctription			
minDate	Unsigned Int	Minumum value of the date field (=0)			
maxDate	Unsigned Int	Maximum value of the date field ($=0xffffffff = 2^{32}-1$)			
Observatory String		Name of the Observatory for which this CalTable is Valid (=LOPES)			
WWFilterS21	Vector <dcomplex></dcomplex>	The S21 of the WainWright filter. (incl. phases)			
WWFilterS21Freq	Vector <double></double>	The frequency axis of the S21 of the WainWright filter.			

(Internal) Structure of the CalTables

			or some time.		

← User Software • CR-Tools

Last

 $\label{localization} \begin{tabular}{ll} update: \\ 2011-10-18 \\ \end{tabular} public: user_software: cr-tools: caltables https://www.astron.nl/lofarwiki/doku.php?id=public: user_software: cr-tools: caltables & rev=1318938725 \\ 11:52 \\ \end{tabular}$

From:

https://www.astron.nl/lofarwiki/ - LOFAR Wiki

Permanent link:

https://www.astron.nl/lofarwiki/doku.php?id=public:user_software:cr-tools:caltables&rev=1318938725

Last update: **2011-10-18 11:52**

